

HP32 Change Control Firmware

Firmware Version V1.5

Enhancements/Improvements:

- Improve the communication missing or idle between meter and probe

Bugs fixed:

- Logging function: Sporadic error description Values come and go, frozen values and values disappeared have been fixed

Known bugs:

- None

Notes:

- ICAN 2021 September
- Firmwareupdate_Procedure_HP32

Firmware Version V1.4

Enhancements/Improvements:

- New display key pad with different On / Off key
- More durable key pad

Bugs fixed:

- None

Known bugs:

- None

Notes:

- None

Firmware Version V1.3

Enhancements/Improvements:

- Max. displayed temperature to 800°C

- Max. displayed of calculated value to 8 digits
- Rename function: Change “Back” to “Delete”
- Adjust capture and log curve to allow the displayed value can be 100000.00 to -10000.00
- Add 4 different languages into memory clearance procedure as waiting reminder
- The adjustable alarm range of all parameters are all amended

Bugs fixed:

- None

Known bugs:

- None

Notes:

- None

Firmware Version V1.2

Enhancements/Improvements:

- Now compatible with HC2-Pt100-B4

Bugs fixed:

- None

Known bugs:

- None

Notes:

- ICAN 2019 March
- Firmwareupdate_Procedure_HP32

Firmware Version V1.1

Enhancements/Improvements:

- None

Bugs fixed:

- HP32 could not display the latest firmware version in “Handheld information” page.

Known bugs:

- None

Notes:

- None